


Integrations: Steam

Allow users to log in and sign up with their Steam account, an option available under .

To set up Steam, you must have a Steam account with at least one paid game purchased recently.






The Steam integration is disabled by default and needs to be activated before use.

1. Visit **Settings -> General -> Third-Party Integrations**.
2. Find the Steam integration and click the "Activate" link located on the left of the table.
3. The page will reload confirming the integration has been activated.

Third-Party Integrations

Successfully updated the third-party integration!

Show 25 entries

Name	Status	Description
 Facebook Activate Uninstall	Inactive	Version 1.0 Author: SupportPal
 Google Activate Uninstall	Inactive	Version 1.0 Author: SupportPal
 Microsoft Activate Uninstall	Inactive	Version 1.0 Author: SupportPal
 Steam Settings Deactivate Uninstall	Active	Version 1.0 Author: SupportPal
 Twitter Activate Uninstall	Inactive	Version 1.0 Author: SupportPal

The integration can be deactivated by following the above process, but using the "Deactivate" link instead.

To set up the Steam integration, you will need a Steam Web API key, follow the steps below.

1. Visit [redacted] and login to your Steam account.
2. Enter the help desk domain when requested and click "Register". You will be given an API key.

Register for a new Steam Web API Key

Registering for a Steam Web API Key will enable you to access many Steam features from your own website.

Domain Name

☒ I agree to the [Steam Web API Terms of Use](#)






[Register](#)

3. Click on Settings under Steam on the third-party integrations page.

Third-Party Integrations

Successfully updated the third-party integration!

Show entries

	Name	Status	Description
	Facebook Activate Uninstall	Inactive	Version 1.0 Author: SupportPal
	Google Activate Uninstall	Inactive	Version 1.0 Author: SupportPal
	Microsoft Activate Uninstall	Inactive	Version 1.0 Author: SupportPal
	Steam Settings Deactivate Uninstall	Active	Version 1.0 Author: SupportPal
	Twitter Activate Uninstall	Inactive	Version 1.0 Author: SupportPal

4. Enter the key given and click "Save".

Steam

API Key

123ABC9C19B7C1CD78986981E5C933EA

Please read over our documentation for setting up Steam.

Save

To enable the Steam login option for your users, follow the steps below.

1. Go to **Settings -> Users -> Social Login**, and click "Manage" on the right of the Steam box. If the option is not there, please ensure you have completed the above set-up of the integration correctly.
2. Press the toggle to enable the social login. If you have multiple brands, you will have the option to enable or disable for each brand.
3. Press "Submit".

It should now be successfully configured, we recommend to try the login as a test user to verify it works.

If you get an "Access Denied" message when trying to request a Steam Web API key, you will need to purchase a paid game.

Online URL: <https://docs.supportpro.vn/article/integrations-steam-23.html>

